



TVFC-OT Adiabatic Cooler Once Through Mode

SOFTWARE INSTRUCTIONS






Table of contents

SOFTWARE INSTRUCTIONS


1	Scope	3
	Once Through execution	3
2	Control Logic	4
3	Programmable logic controller	6
	Progammable Logic Controller (PLC)	6
	Display and operations	6
4	Software	8
	Menu overview	8
	Main Loop Menu (P)	9
	User Menu (E)	10
	Working Time Menu (T)	15
	Inputs Outputs Menu (I)	16
	Clock Menu (K)	17
	Logger Menu (H)	17
	System Information (S)	18
	Maintenance Menu (M)	18
5	Alarms and Warnings overview	20
	Alarms overview	20
6	BMS Communication	22
	Available communication protocols and communication cards	22
	Communication table for Bacnet MS/TP	23
	Commissioning guide Bacnet MSTP	26
7	Further Assistance & Information	38
	More information	38
	The service expert for BAC equipment	38



This manual applies to units configured in Once-Through mode operating on BAC software version V2.0.15 or later, in stand-alone mode.

Once Through execution


The TVFC is a V-shaped dry cooler equipped with adiabatic pre-coolers (1) that cool the warm process fluid (2) by sensible heat transfer. Water flows (3) evenly over evaporative cooling pads located in front of the dry finned coil (4). At the same time axial (5) fans draw air (6) through the pads where a portion of the water evaporates and cools down the saturated air. This increases the cooling capacity of the incoming air for cooling the process fluid (7) inside the coil.





The controller controls the fan speed based on the actual fluid outlet temperature and the standard or freecooling set point, ensuring a minimum electrical consumption and noise level.

The controller will activate and deactivate the adiabatic pre-coolers, one by one, based on a logical combination of fan speed and two ambient temperature switch points.



tamb: ambient temperature

SWP1, SWP2: ambient temperature switchpoints

CWV: adiabatic pre-cooler city water valve

DV: adiabatic pre-cooler drain valve

The standard set point, the free-cooling set point and the two ambient temperature set points are adjustable via the User menu. The controller continuously measures the fluid outlet temperature via a temperature sensor installed in the fluid out pipe and the ambient temperature via a temperature sensor that is factory installed on the unit.

The controller is pre-programmed and ready for operation. However, depending on the size of the installation, you may need to adjust the pre-programmed parameters during start-up.



CAUTION

Changing the PLC's parameters may result in an undesired operation of the unit such as a hunting phenomenon, premature activation of pre-cooling (hence increased water consumption) or in late pre-cooling activation resulting in fluid outlet temperatures exceeding the design temperature.



Progammable Logic Controller (PLC)

The PLC with built-in display:



Display and operations

The controller display contains the screen and six operation keys.

The screen allows eight lines of text. The screen title and the screen reference are always on the top line. Use the operation keys to navigate between the different menus and screens.

	Alarm key	Display the alarm menu.
\odot	Menu key	Display the main menu screen.

ち	Back key	Revert to the previous step or menu.	BAC
↓ ↑	Arrow keys	Navigate between the different screens and menus.	
4	Enter key	Select the marked menu or parameter or enable the change of a parameter.	



Menu overview

Menu	Screen reference	Function
Main loop	Ρ	 Readout: The unit status (ON/OFF) The fluid outlet and ambient temperature The fan speed The pre-cooler status
User	E	 Set: Run authorisation / local ON/OFF Standard and free-cooling set-point PI parameters Ambient temperature switch point for Adiabatic pre-cooling Adiabatic pre-cooler delay Adiabatic pre-cooler cleaning cycle Night quiet mode Time delay on alarm messages BMS communication settings The standard password for the User Menu is "1234".
Manufacturer	С	This menu is password protected and is not accessible to unauthorized personnel.
Working time	Т	Readout the operating hours for the fans and adiabatic pre-cooling.
Inputs/outputs:	I	Readout the input and output status.
Clock	K	Set the correct time and date.
Logger	Н	Readout the alarm and warning history.
System info	S	Readout the software and bios version.
Maintenance	М	Set the inputs and outputs manually for test purposes. The standard password for the Maintenance menu is "9876".

Main Loop Menu (P)





The screens in the Main Loop Menu are read-only and cannot be edited.

Screen P01

5151H 515 BACH1607697	
Seteoint	00.0°C
Tout	00.0 °C
Tamb	00.0 °C
Fan speed	000.0 %
	06.61

Main screen with general information:

- The current time and date.
- The unit serial number and pLAN address: "Ad: 0".
- "Setpoint": the active setpoint for the fluid outlet temperature.
- "Tout": the measured fluid outlet temperature.
- "Tamb": the measured ambient temperature.
- "Fan speed": the current fan speed.
- The unit status: "ON" or "OFF".

Note

Unit status ON implies that the unit is ready to automatically respond to any heat rejection requirement, even in case the fans are temporarily deactivated due to the absence of a heat load.

Screen P03

Tout Tout	208.0°C
Tamb Control	000.0 °C si9nal000.0 %
Local Er BUS En/D	Dis OFF

Overview of all inputs:

- "Tout": the measured fluid outlet temperature.
- "Tamb": the measured ambient temperature.
- "Control signal": the calculated fan speed reference.
- "Local En/Dis": the status of the remote start/stop (dry contact between terminals Y4:1-Y4:4).
- "BUS En/Dis": the status of the BMS controlled variable "Run authorization" (refer to screen E02).

Screen P04

Pre-cooling	문화전
Pre-cooler A	OFF
Pre-cooler B	OFF

Adiabatic pre-cooling status:

- "Pre-cooler A": shows the status of the adiabatic pre-cooler on side A.
- "Pre-cooler B": shows the status of the adiabatic pre-cooler on side B.

Screen P10-P51



rem#fo EBM fan N°2 B10 Offline Addr:002 Current speed 0000rpm Max speed 00000 rpm Power 00000W Current 00000 mA

EC fan information screens:

- The fan status: "Online" or "Offline" and fan address: "Addr: 002".
- "Current speed": the actual fan speed.
- "Max speed": the maximum allowable fan speed.
- "Power": the actual power of the EC fan.
- "Current": Indication of the internal current measured by the EC fan. In most cases this value is a DC current
 which is typically around 1.42 times bigger as the actual current, but for specific type of EC fans the AC
 current could be displayed. For exact evaluation of the fan current please measure the current on the
 terminal strip using an Amperage meter.

Note

In case an EC fan shows the status "Offline", check the power supply to the fan and the Modbus communication wiring to the fan.

User Menu (E)

The screens in the User Menu are editable. The standard password is "1234".


P

Screen E01



- "Language": set the controller language to English, French, Dutch, Spanish or German.
- "Site name": enter the unit serial number or the site name.

Screen E02



- "Run authorization": activate or deactivate the unit. This variable can either be set directly in this screen or via a BMS variable (see section 6: BMS communication).
- "Standard setpoint": the default setpoint for the fluid outlet temperature.
- "Free cooling setpoint": the setpoint for the fluid outlet temperature when the unit operates in free cooling mode. Switch over to free cooling mode via a BMS controlled variable or via the dry contact between terminals Y4:2-Y4:4.

Example

10

The controller controls the fan speed based on the actual fluid outlet temperature and the standard setpoint when the dry contact between terminals Y4:2-Y4:4 is open. When the dry contact between terminals Y4:2-Y4:4 is closed, the controller controls the fan speed based on the actual fluid outlet temperature and the free cooling setpoint.


Screen E03





PI-parameters: these parameters determine the unit's reaction speed to changes in fluid outlet temperature.

- "Prop. Band": set the value for the proportional band of the PI controller.
- "Integr. Time": set the value for the integration time of the PI controller.



band and the integration time, or make the unit react slower by increasing the proportional band and integration time.

Screen E04



Cleaning cycle for the adiabatic pre-coolers:

- "PAD cleaning": allows you to enable or disable the cleaning cycle function. •
- "Interval": set the period (the number of days the adiabatic pre-cooling has not functioned) after which the cleaning cycle must activate.
- "Duration": set the duration for the pre-cooler cleaning cycle.
- Set the time interval for the start of the cleaning cycle.

Example

The pre-cooler cleaning cycle activates the pre-coolers during 120 minutes when the unit has not operated adiabatically for a period of 7 days. The cleaning cycle starts between 14h00 and 18h00.

Note

The controller automatically disables the cleaning cycle when the ambient temperature is below 4°C.

Screens E05-E06



Adiabatic pre-cooler temperature and fan speed switchpoints and time delays:

- "AD switchpnt.1" and "AD switchpnt.2": the temperature switchpoints for the activation of the adiabatic pre-coolers.
- "AD ON fan speed" and "AD OFF fan speed": the fan speed switchpoints for the activation and • deactivation of the adiabatic pre-coolers.
- "AD ON delay" and "AD OFF delay": the time delays for the activation and deactivation of the adiabatic pre-• coolers.



- **Example** The first pre-cooler will activate when the ambient temperature > 25.0°C**AND** the fan speed > 99%, after a 300 seconds delay.
 - The second pre-cooler will activate when the ambient temperature > 28.0°C AND the fan speed > 99% after a 300 seconds delay.
 - The first pre-cooler will deactivate when the ambient temperature < 27.9°C
 - **OR** the fan speed < 70% after a 30 seconds delay.
 - The second pre-cooler will deactivate when the ambient temperature > 24.9°C OR the fan speed < 70% after a 30 seconds delay.

Note


The temperature and fan speed switchpoints determine the operating strategy of the unit. High temperature switchpoints combined with high fan speed switchpoints typically result in high water savings on the adiabatic pre-cooling, while lower temperature and fan speed switchpoints typically result in higher electrical energy savings on the EC fans.

Screens E10-E11-E12

Night Quiet mode E10	DAYTIME	E11	Night Quiet m	ode E12
Night Quiet Mode	MON from00H00	to00H00	AD switchpoint:	
OFF	TUE from00H00		in night quiet	mode
	WED from00H00			
Daytime s.limit 100.0%	THU from00H00		Switchent.1	15.0°C
Night s.limit 080.0%	FRI from00H00		Switchent.2	18.0°C
	SAT from00H00 SUN from00H00			
Control: Clock	SUN from00H00	to00H00		

Night quiet mode: predefine fan speed limits for both day and night time.

- Enable/Disable the Night quiet mode and choose the maximum allowed fan speed during day and night on screen E10:
 - "Night quiet mode": "ON" or "OFF": enable or disable the Night quiet mode.
 - "Daytime speed limit" and "Night time speed limit": set the maximum allowed fan speed during day and night time.
 - "Control": choose the activation mode: either via a BMS controlled variable ("via BMS") or via a predefined time daytime schedule in screen E11("Clock").
 - **"Daytime clock**"Set up a time schedule for the daytime speed limit in screen E11: Monday to Sunday, start time to end time.



- "Via BMS": Use parameter "Night quiet mode day/night time speed limit via BMS" to switch between daytime speed limit and night time speed limit (Refer to the communication tables in Chapter 6).
- Set specific adiabatic pre-cooler switchpoints for Night quiet mode operation in screen E12:
 - **"AD switchpnt.1**" and **"AD switchpnt.2**": specific temperature switchpoints for the activation of the adiabatic pre-coolers when the night time speed limit is active.



Example The Night quiet mode is enabled, with a daytime speed limit of 80% and a night time speed limit of 50%.

During daytime:

- The first pre-cooler will activate when the ambient temperature > 25.0°C **AND** the fan speed > 79.2% (= 99% x 80%) after a 300 second delay.

- The second pre-cooler will activate when the ambient temperature > 28.0°C **AND** the fan speed > 79.2% after a 300 second delay.

- The first pre-cooler will deactivate when the ambient temperature < 27.9°C **OR** the fan speed < 56% (= 70% x 80%) after a 30 second delay.

- The second pre-cooler will deactivate when the ambient temperature > 24.9°C **OR** the fan speed < 56% after a 30 second delay.

During night time:

- The first pre-cooler will activate when the ambient temperature > 15.0°C **AND** the fan speed > 49.5% (= 99% x 50%) after a 300 second delay.

- The second pre-cooler will activate when the ambient temperature > $18,0^{\circ}$ C **AND** the fan speed > 49.5% (= $70\% \times 80\%$) after a 300 second delay.

- The first pre-cooler will deactivate when the ambient temperature < 17.9 °C **OR** the fan speed < 35% (= 70% x 50%) after a 30 second delay.

- The second pre-cooler will deactivate when the ambient temperature < 14.9°C **OR** the fan speed < 35% after a 30 second delay.

Screen E14



Adiabatic pre-cooling deactivation function:

- "Pre-cooler deact.": enable or disable the pre-cooler deactivation function.
- Set the period and the time frame during which the unit deactivates the adiabatic pre-cooling.

Example

When the pre-cooling deactivation function is active, the adiabatic pre-cooling cannot activate between 13:00 and 15:00 o'clock from 15/07 to 15/09.

Screen E15

Forced AD op. Forced AD op. (Authorisation:	mode OFF
Setp. hyst. AD act. delay Ma/SI unit del.	001min

The forced adiabatic operation function allows the unit to activate both pre-coolers simultaneously when the ambient temperature exceeds the fluid outlet setpoint.

- "Forced AD op. mode authorization": enable or disable the forced adiabatic operation function.
- "Setp. hyst.": hysteresis on the fluid outlet temperature setpoint.
- "AD act. Delay": time delay for the activation of the forced adiabatic operation mode.
- "Ma/SI unit delay": time delay for the activation and deactivation of the pre-cooling in forced adiabatic operation mode.

BAC

Forced AD op. E16 Forced AD op. Min fan speed 040 % Max fan speed 090 %

- "Min fan speed": fan speed switchpoint for deactivation of the pre-cooling in the forced adiabatic operation mode.
- **"Max fan speed**": fan speed switchpoint for activation of the pre-cooling in the forced adiabatic operation mode.

Example

Screen E16

The forced adiabatic mode activates when Tamb > ("setpoint" + "setp. hyst.") > $(30^{\circ}C + 0^{\circ}C) > 30^{\circ}C$ during 1 minute.

While in forced adiabatic mode, the pre-cooling activates and deactivates as follows: - When the fans operate between 90% ("**Max fan speed**") and 99%, the pre-cooling activates after 60 s ("**Ma/SI unit delay**").

- When the fans operate at full speed (100%), the pre-cooling activates after 5 s.
- When the fans operate between 30% and 40% ("**Min fan speed**"), the pre-cooling deactivates after 60 s ("**Ma/SI unit delay**").
- When the fans stop running, the pre-cooling deactivates immediately.

Screen E17



Choose the communication protocol: Modbus RS485, Modbus IP, Carel RS485, LON, BacNet IP or BacNet MSTP. Set the communication speed and network address, when applicable. See section 6: BMS communication.

Screen E18



Alarm detection delays:

- "Alarm delay": time delay for EC fan alarms and warnings.
- "Sensor alarm delay": time delay for alarms from the fluid outlet temperature and ambient temperature sensor.
- "Network comm. Loss delay": time delay for the loss of pLAN communication between units (not applicable for stand-alone operation).

```
Note
```

The network communication loss delay is not applicable to stand alone operation.

Screens E19-E20



EC fan emergency mode management:

Enable the EC fan emergency mode to select a fixed fan speed for when the Modbus communication between the controller and the EC fans fails.

In case the EC fan emergency mode is disabled, the fans will continue to operate at the latest known fan speed when the Modbus communication between the controller and the EC fans fails.



- "Emergen. mode": "ON" or "OFF": enable or disable the EC fan emergency mode.
- "Timeout": time delay before the EC fan emergency mode activates.
- **"EM speed 1**": the emergency speed reference in case the ambient temperature ≥ the ambient temperature switchpoint.
- **"EM speed 2**": the emergency speed reference in case the ambient temperature < the ambient temperature switchpoint.
- "Switch Tamb": the ambient temperature switchpoint.

Example When the EC fan emergency mode is enabled, EM speed 1 is set to 100%, EM speed 2 is set to 50% and Switch Tamb is set to 15°C, the EC fans will start running at a fixed speed of 100% in case the Modbus communication between the controller and the EC fans fails when the ambient temperature is 20°C.

In case, the Modbus communication between the controller and the EC fans fails when the ambient temperature is 10°C, the EC fans will start running at a fixed speed of 50%.

Screen E21



Set your own access code for the User Menu.

Working Time Menu (T)

The screens in the Working Time Menu are read only and cannot be edited.

Screen T02

Operating	time T02
Fans	000000H
Step 1 AD Step 2 AD	000000H 000000H

Read the operating time for the EC fans and for both adiabatic pre-coolers, displayed in hours.

Screen T03

T A S
өөн
өөн


Read the operating time for the EC fans, both adiabatic pre-coolers, and the dry and adiabatic operating time displayed in hours.



Inputs Outputs Menu (I)

The screens in the Inputs/Outputs Menu are read only and cannot be edited.

Screens 101-102



Read the analog inputs on the controller:

- "U1: T°C Tout": the current fluid outlet temperature.
- "U2: T°C Tgen": not used.
- "U3: T°C Tamb": the current ambient temperature.

Screen I03



Read the status of the digital inputs on the controller (open/closed):

- "ID4-DI: Inverter AI": VFD status (not used in case of unit working with EC fans).
- "ID5-DI: Free cooling": status of the free cooling mode (dry contact between terminals Y4:2-Y4:4).
- "ID1: On-Off": status of the remote start/stop command (dry contact between terminals Y4:1-Y4:4).
- "U5: Fan Al": not used.


Screen I04

Inputs/Outputs	104
NO8:Alarm(s)	
N07:Warning(s)	
NO3:Pre-Cooler.R	
NO2:Pre-Cooler.L	
N05:	
NO6:Operational	
□lopen - ∎tclosed	

Read the status of the digital outputs on the controller (open/closed).

- "NO8: Alarm(s)": closed contact means that there are one or more alarms active.
- "NO7: Warning(s)": a closed contact means that there are one or more warnings active.
- "NO3: RH Pre-cooler": a closed contact means that the right pre-cooler is active.
- "NO2: LH Pre-cooler": a closed contact means that the left pre-cooler is active.
- "NO5: ---": not used.
- "NO6: Operational": run indication, a closed contact means that the fans are running.

Screen I05




Read the analog outputs on the controller:

- "Y3: N.U": not used.
- "Y4: Fan speed": a 0-10 Volt control signal, which corresponds to the actual fan speed. (0 V = 0%, 10 V = 100%)

Clock Menu (K)



Screen K01



Set the correct time and date. Time format: HH:MM:SS and date format: DD/MM/YY. The software automatically adjusts to Daylight Saving Time.

Logger Menu (H)

The screens in the Logger Menu are read only and cannot be edited.

Screen H01



Read the history of past alarms.

The log shows the alarm message and the time the alarm occurred.






System Information (S)

The screens in System Information are read only and cannot be edited.

Screen S01



"SW Ver.": Current software version installed "OS Ver.": Operating system version "BOOT Ver.": Current boot version

Maintenance Menu (M)


Screen M01

MAINTENANCE	MØ1
Sensor offset Dutlet (U1) 000.0	• C
Corr.:000.0 °C General (U2) 000.0	• C
Corr.:000.0 °C Tamb (U3) 0000.0 Corr.:000.0 °C	°C

Program a sensor offset ("**Corr.**:") to correct the temperature readings for the fluid outlet temperature sensor ("**Outlet (U1)**") and the ambient temperature sensor ("**Tamb (U3)**").

The general outlet temperature sensor is not used in stand-alone operation.

Screen M02



Activate the test mode, which allows to manually set analog and digital outputs and control the EC fans.

• **"Test mode**": activate or deactivate the test mode.

• "Duration": time delay after which the test mode automatically deactivates.

Note

Duration set to 99 min keeps the test mode ON indefinitely
 When the test mode is set to OFF, screens M03 to M07 are invisible.

Screen M03

Dig.out over	ride	103
Pre-cooler R	(NØ3):	
	(NØ2):	
Run indicat.	(NØ6):	
Alarm	(108):	
Warning	(NØ7):	
□:Open / ∎ :	Closed	

Manually set the digital outputs:

- "Pre-cooler R": activate or deactivate the right hand pre-cooler.
- "Pre-cooler L": activate or deactivate the left hand pre-cooler.
- "Run indicat.": simulate the run indication.
- "Alarm": simulate an alarm.
- "Warning": simulate a warning.

Screen M05



Manually set the analog outputs:

- "Y3": not used for a unit with EC fan motors.
- "Y4": simulate a 0-10 Volt output.

Screen M06



Manually control the EC fans:

- "Fan speed": 0% to 100%
- "Control type": choose "Global" to operate all fans simultaneously at the same speed or choose "1 by 1" to set the speed for each fan individually via screen M07.

Screen M07

Tes	st indi	v. fat	ns M07
Nº 2	000-0%	Nº 9	000-0%
Nº 3	000-0%	Nº 10	000-0%
Nº 4	888-8%	Nº 11	888-8%
Nº 5	000-0%	Nº 12	000-0%
Nº 6	000-0%	Nº 13	000-0%
Nº 7	000-0%	Nº 14	000-0%
Nº 8	000-0%	Nº 15	000-0%

Set the speed for each fan individually.





Alarms overview

- Access the alarms by pressing the alarm button on the controller (triangle with exclamation mark).
- If a particular alarm is no longer present, the alarm message is automatically cleared and the general alarm (NO1) deactivates.
- To see the history of past alarms, check the logger menu.

Note

The Alarm status can be read out via dry contact on terminal Y3: 3/4/5 and the warning status on Y3: 1/2 in the control panel.

Screen AL000

No alarm present.



Screen AL001



Fluid outlet temperature sensor (on input U1) is defective.

- Unit stops working.
- Alarm message AL001 on controller display + general alarm (NO1) activates.





Ambient air temperature sensor (on input U3) is defective.

- Unit remains operational in dry mode, adiabatic operation no longer possible.
- Alarm message AL003 on controller display + general alarm (NO1) activates.

Screens AL010-AL106



Alarms and warnings from the EC fans. Consult BAC factory for more information.

• Unit remains operational, but the defective fan stops working.





Available communication protocols and communication cards

The following communication protocols are available: Carel RS485, Modbus RS485, Modbus TCP/IP, Bacnet IP, Bacnet MS/TP and LON. The table below shows the required communication card and software settings for each communication protocol.



Based on your selection, this manual will only contain the information you require.

Protocol	Communication card reference	Typical parameter settings in the controller	Interface file required?	Available settings
CAREL RS485		Supervision E17 BMS communication CAREL R5485 Baud rate 19200 Address 001	No	- Baudrate: 1200 to 19200 - Slave addresses: 1 to 207
Modbus RS485		Supervision E17 BMS communication Modbus RS485 Baud rate 19200 Address 001 Parity None Stop Bit 2	No	- Baudrate: 1200 to 19200 - Parity: None, Even or Odd - Nbr. stop bits: 1 or 2 - Slave addresses: 1 to 207
Modbus TCP/IP		Supervision E17 BMS communication Modbus IP	No	
Bacnet IP		Supervision E17 BMS communication Bacnet IP	No	

Protocol	Communication card reference	Typical parameter settings in the controller	Interface file required?	Available settings
Bacnet MS/TP		Supervision E17 BMS communication Bacnet MS/TP	No	
LON		Supervision E17 BMS communication Lon	Yes (Xif and Nxe file)	

Communication table for Bacnet MS/TP

			BACNET MS/TP			
Variable	UOM	R/W	Obj_ Type	Obj_ Instance	Obj_ Name	
Fluid outlet temperature	°C	R	analog	1	A001	
Ambient temperature	°C	R	analog	3	A003	
AD switchpoint 1	°C	R/W	analog	4	A004	
AD switchpoint 2	°C	R/W	analog	5	A005	
Night quiet mode: AD switchpoint 1	°C	R/W	analog	8	A008	
Night quiet mode: AD switchpoint 2	°C	R/W	analog	9	A009	
Active setpoint	°C	R	analog	10	A010	
Regular setpoint	°C	R/W	analog	11	A011	
Free cooling setpoint	°C	R/W	analog	12	A012	
Proportional band	°C	R/W	analog	15	A015	
Night quiet mode: daytime speed limit	%	R/W	analog	16	A016	
Night quiet mode: night time speed limit	%	R/W	analog	17	A017	
Daytime clock: Monday start hours	h	R/W	analog	1006	1006	
Daytime clock: Monday start minutes	m	R/W	analog	1007	1007	
Daytime clock: Monday end hours	h	R/W	analog	1008	1008	
Daytime clock: Monday end minutes	m	R/W	analog	1009	1009	
Daytime clock: Tuesday start hours	h	R/W	analog	1010	1010	
Daytime clock: Tuesday start minutes	m	R/W	analog	1011	I011	
Daytime clock: Tuesday end hours	h	R/W	analog	1012	1012	
Daytime clock: Tuesday end minutes	m	R/W	analog	1013	1013	
Daytime clock: Wednesday start hours	h	R/W	analog	1014	I014	
Daytime clock: Wednesday start minutes	m	R/W	analog	1015	I015	
Daytime clock: Wednesday end hours	h	R/W	analog	1016	1016	
Daytime clock: Wednesday end minutes	m	R/W	analog	1017	1017	
Daytime clock: Thursday start hours	h	R/W	analog	1018	1018	
Daytime clock: Thursday start minutes	m	R/W	analog	1019	1019	
Daytime clock: Thursday end hours	h	R/W	analog	1020	1020	
Daytime clock: Thursday end minutes	m	R/W	analog	1021	1021	
Daytime clock: Friday start hours	h	R/W	analog	1022	1022	
Daytime clock: Friday start minutes	m	R/W	analog	1023	1023	
Daytime clock: Friday end hours	h	R/W	analog	1024	1024	
Daytime clock: Friday end minutes	m	R/W	analog	1025	1025	



				BACNET MS/TP	
Variable	UOM	R/W	Obj_ Type	Obj_ Instance	Obj_ Name
Daytime clock: Saturday start hours	h	R/W	analog	1026	1026
Daytime clock: Saturday start minutes	m	R/W	analog	1027	1027
Daytime clock: Saturday end hours	h	R/W	analog	1028	1028
Daytime clock: Saturday end minutes	m	R/W	analog	1029	1029
Daytime clock: Sunday start hours	h	R/W	analog	1030	1030
Daytime clock: Sunday start minutes	m	R/W	analog	1031	1031
Daytime clock: Sunday end hours	h	R/W	analog	1032	1032
Daytime clock: Sunday end minutes	m	R/W	analog	1033	1033
Night quiet mode - Control type (0: clock - 1: via BMS)		R/W	analog	1034	1034
Integration time	sec	R/W	analog	1036	1036
Cleaning cycle: interval	days	R/W	analog	1037	1037
Cleaning cycle: duration	min	R/W	analog	1038	1038
AD ON fan speed	%	R/W	analog	1039	1039
AD OFF fan speed	%	R/W	analog	1040	1040
AD ON delay	sec	R/W	analog	1041	1041
AD OFF delay	sec	R/W	analog	1042	1042
Unit pLAN address		R	analog	1050	1050
Pre-cooling Deactivation function: start day		R/W	analog	1055	1055
Pre-cooling Deactivation function: start month		R/W	analog	1056	1056
Pre-cooling Deactivation function: end day		R/W	analog	1057	1000
Pre-cooling Deactivation function: end month		R/W	analog	1058	1058
Pre-cooling Deactivation function: start hour	h	R/W	analog	1059	1050
Pre-cooling Deactivation function: end hour	h	R/W	analog	1059	1053
Alarm delay		R/W		1067	1001
Sensor alarm delay	sec	R/W	analog	1067	1067
-	sec %		analog	1008	1008
Fan speed		R	analog		_
EC fan N°2: actual speed	rpm	R	analog	1077	1077
EC fan N°2: maximum allowable speed	rpm	R	analog	1078	1078
EC fan N°2: actual power	W	R	analog	1079	1079
EC fan N°3: actual speed	rpm	R	analog	1081	1081
EC fan N°3: maximum allowable speed	rpm	R	analog	1082	1082
EC fan N°3: actual power	W	R	analog	1083	1083
EC fan N°4: actual speed	rpm	R	analog	1085	1085
EC fan N°4: maximum allowable speed	rpm	R	analog	1086	1086
EC fan N°4: actual power	W	R	analog	1087	1087
EC fan N°5: actual speed	rpm	R	analog	1089	1089
EC fan N°5: maximum allowable speed	rpm	R	analog	1090	1090
EC fan N°5: actual power	W	R	analog	1091	1091
EC fan N°6: actual speed	rpm	R	analog	1093	1093
EC fan N°6: maximum allowable speed	rpm	R	analog	1094	1094
EC fan N°6: actual power	W	R	analog	1095	1095
EC fan N°7: actual speed	rpm	R	analog	1097	1097
EC fan N°7: maximum allowable speed	rpm	R	analog	1098	1098
EC fan N°7: actual power	W	R	analog	1099	1099
EC fan N°8: actual speed	rpm	R	analog	1101	l101
EC fan N°8: maximum allowable speed	rpm	R	analog	1102	1102
EC fan N°8: actual power	W	R	analog	1103	I103
EC fan N°9: actual speed	rpm	R	analog	1105	I105
EC fan N°9: maximum allowable speed	rpm	R	analog	1106	I106
EC fan N°9: actual power	W	R	analog	1107	I107
EC fan N°10: actual speed	rpm	R	analog	1109	I109
EC fan N°10: maximum allowable speed	rpm	R	analog	1110	I110
EC fan N°10: actual power	W	R	analog	1111	1111

				BACNET MS/TP	
Variable	UOM	R/W	Obj_ Type	Obj_ Instance	Obj_ Name
EC fan N°11: actual speed	rpm	R	analog	1113	1113
EC fan N°11: maximum allowable speed	rpm	R	analog	1114	I114
EC fan N°11: actual power	W	R	analog	1115	l115
EC fan N°12: actual speed	rpm	R	analog	1117	l117
EC fan N°12: maximum allowable speed	rpm	R	analog	1118	l118
EC fan N°12: actual power	W	R	analog	1119	l119
EC fan N°13: actual speed	rpm	R	analog	1121	l121
EC fan N°13: maximum allowable speed	rpm	R	analog	1122	l122
EC fan N°13: actual power	W	R	analog	1123	I123
EC fan N°14: actual speed	rpm	R	analog	1125	l125
EC fan N°14: maximum allowable speed	rpm	R	analog	1126	l126
EC fan N°14: actual power	W	R	analog	1127	l127
EC fan N°15: actual speed	rpm	R	analog	1129	l129
EC fan N°15: maximum allowable speed	rpm	R	analog	1130	I130
EC fan N°15: actual power	W	R	analog	1131	l131
Standard/Free cooling switch over (0: Standard / 1: Free cooling)		R/W	binary	1	D001
Free cooling status (0: OFF / 1: ON)		R	binary	2	D002
Night quiet mode (0: disable / 1: enable)		R/W	binary	4	D004
Night quiet mode status (0: not active / 1:active)		R	binary	5	D005
Night quiet mode: clock mode active (0: NO / 1: YES)		R	binary	6	D006
Night quiet mode: BMS mode active (0: NO / 1: YES)		R	binary	7	D007
Night quiet mode day/night time speedlimit via BMS (0: night / 1: day)		R/W	binary	8	D008
Run authorization (0: OFF / 1: ON)		R/W	binary	9	D009
Cleaning cycle (0: disable / 1: enable)		R/W	binary	10	D010
Pre-cooling deactivation function (0: disable / 1: enable)		R/W	binary	11	D011
NO1 relay output status - Alarm(s) (0:No Alarm / 1:Alarm)		R	binary	13	D013
NO2 relay output status- Warning(s) (0:No Warning / 1:Warning)		R	binary	14	D014
NO3 relay output status- RH pre-cooler (0:open / 1:closed)		R	binary	15	D015
NO4 relay output status - LH pre-cooler (0:open / 1:closed)		R	binary	16	D016
NO6 relay output status - Run indication (0:Stopped / 1:Running)		R	binary	18	D018
B6 Dig In status - Free cooling mode (0: Disabled / 1: Enabled)		R	binary	21	D021
ID1 (0: Off / 1:On) - Remote start/stop status		R	binary	22	D022
Alarm sensor B1 (fluid outlet temperature sensor)		R	binary	24	D024
Fan N°2 - alarm/warning present		R	binary	29	D029
Fan N°3 - alarm/warning present		R	binary	30	D030
Fan N°4 - alarm/warning present		R	binary	31	D031
Fan N°5 - alarm/warning present		R	binary	32	D032
Fan N°6 - alarm/warning present		R	binary	33	D033
Fan N°7 - alarm/warning present		R	binary	34	D034
Fan N°8 - alarm/warning present		R	binary	35	D035
Fan N°9 - alarm/warning present		R	binary	36	D036
Fan N°10 - alarm/warning present		R	binary	37	D037
Fan N°11 - alarm/warning present		R	binary	38	D038
Fan N°12 - alarm/warning present		R	binary	39	D039
Fan N°13 - alarm/warning present		R	binary	40	D040
Fan N°14 - alarm/warning present		R	binary	40	D040
Fan N°15 - alarm/warning present		R	binary	41	D041

BAC



				BACNET MS/TP	
Variable	UOM	R/W	Obj_ Type	Obj_ Instance	Obj_ Name
Alarm present		R	binary	59	D059
Unit status (0: OFF / 1: ON)		R	binary	63	D063
Warning present		R	binary	66	D066
Alarm sensor B4 (ambient temperature sensor)		R	binary	67	D067

Commissioning guide Bacnet MSTP

This section will show the commissioning procedure to activate the Carel PLC with the Bacnet MS/TP protocol.

Requirements:

- PC/Laptop
- RS485 to USB converter
- Carel PLC wiht Carel pCONet card

The following steps are covered in this section:

- 1. Hardware setup
- 2. Check the configuration of the Carel PLC
- 3. PC configruation
- 4. Configuration of the pCONet card
- 5. Common connection errors
- 6. Test via BACset

HARDWARE SETUP

Make sure the Carel pCONet card is installed on the Carel PLC.



Connect the serial card to your laptop by using the RS485 to USB converter.



Make sure that the polarity of the wiring between the serial card and the convertor is correct. The wiring should be as follows:

Rx+/Tx+ -> +

Rx-/Tx- -> -

It might be possible that other convertor suppliers use other terminology. In this case they will probably use the next descriptions.

A -> +

B -> -

Do not connect the GND connection when you use the convertor in combination with your laptop. You might get wrong readouts when the GND is connected to your laptop. The GND connection only needs to be used when connecting the serial card with the customer network.

Now power the controller.

CAREL PLC CONFIGURATION

Make sure that the Carel PLC is configured correctly.

- Go to the User (E) menu
- Enter the password "0000"
- Go to the User screen E17
- Define the protocol as Bacnet MS/TP



PC CONFIGURATION

For this example, we used Microsoft Windows 10.


Download virtual COM port drivers

Virtual COM port (VCP) drivers make the USB device to appear as an additional COM port available on the PC. Application software can access the USB device in the same way as it would access a standard COM port. You can download the software via https://ftdichip.com/drivers/vcp-drivers/

DONWLOAD BACSET SOFTWARE

BACset is the software that is used to execute the configuration on the pCONet interface card. Please follow the next steps to download the BACset software.

- 1. Go to the Carel Knowledge Sharing Area (KSA): https://ksa.carel.com/group/ksa/home
- 2. Create an account and log in
- 3. Once logged in, select Software and Support (Sw&Support)



4. Select pCOWeb/pCONet



5. Select the pCONet SE tab



6. Scroll down and select the BACset folder

Title	Size	
BAGset	*	0
Eirmware	72	0
🔒 Plugin	<u>11</u>	0
2 pCOnetSE	96	0


7. Download the installation file and execute the installation

Title	Size	
Display BACset Users Guide 215 pdf	896	0
Contemporary BACset_2.15.4.exe.pdf	231	0
BACSet_INSTALLER.zip	1,281	0
How to replace BACset exe.pdf	208	0
COnet PICS 2 15.4 pdf	155	0

The original version of the software is installed (V2.15). It is necessary to replace this original .exe file to update the software.


8. Download the new version of the software (V2.15.4)







9. Copy the latest downloaded and updated version from your download files.



10. The original download is stored in the next foler: C\Program Files (x86)\Carel\BACset

Paste the copied file in this folder. You will be asked to override the original source file since this file has the same file name. Click OK.

de Home Share View					
🚽 👻 🕇 📕 > This PC >	Local Disk (C:) > Program	m Files (x86) > Carel > BACset	~	U	, Search BACset
1011	^	Name ^			Date modified
* Quick access		Drivers			17/12/2021 13:46
Documents	34	BACset Users Guide 215.pdf			14/12/2011 16:33
Downloads		C bacset.exe			4/03/2022 10:00
E Pictures	*	bacset.oldexe			14/12/2011 16:33
technische informatie	* ~ <				1910201110000

Now the software is downloaded, and the latest update was executed as well.

PCONET CARD CONFIGURATION

Start up with Factory settings

Power the Carel PLC again while pushing the setup button on the pCONet card. The status LED will be green. Hold the button. After ± 10 seconds, the LED will start flashing red slowly. Release the button before the LED flashed red 3 times. Now the pCONet card is started with the factory settings.





Parameter	Min	Max	Factory
Device instance	0	4194303	77000
Station Address	0	127	0
MaxMaster	0	127	127
Max Info Frames	0	255	20
BaudRate	9600-192	00-38400-76800	38400

Meaning of the Status LED

Once the starting sequence has been completed, the "Status LED" flashes to indicate the quality of communication between the PLC and the card:

Quick green-OFF-greencommunication with the card is OK (card ON-LINE)Slow red-OFF-redcommunication with the cards has not been established (card OFF-LINE)Green-red-greencard detects errors or a temporary lack of response

Meaning of the Network LED

The Netword LED indicates the status of communication with the BACnet MS/TP network (RS485).

Starting sequence:

After power-up or after rebooting the card, the Neword LED switches in the following sequence

- off for about 45 seconds
- then the card shows slow green-red-green-red
- after this sequence the BACnet is active

Status of communication with the BACnet MS/TP network:

Once the starting sequence has been completed, the Network LED flashes to indicate the quality of communication between the BACnet MS/TP network and the pCONet card.

Green with occasional red flashes Communication is OK

Steady red LED light

Communication is not established (connection problems or no network device found). This may depend on electrical connection difficulties or communication settings that are not compatible with the other network devices connected

Adjust port settings

Make sure that the pCONet card is connected with your laptop by using the converter. The BACset software will try to connect with the controller by using COM1. Therefore, we need to make sure that the settings of the COM port that we use is correct and set to port 1.



Open the "Device Manager" via your control panel (or search) to confirm the port number and setting.

D 🖻	evice Manager — 🗆 🗙
File	Action View Help
(= =)) III 🔛 🔛 🛒
- 4	PF132Y0J ^
2.	Audio inputs and outputs
2	Patteries
	Biometric devices
	3 Bluetooth
- it	P Cameras
- 6	Computer
- 8	Disk drives
2	The Display adapters
	Firmware
5	Human Interface Devices
÷.	🛄 Keyboards 🥢
- 10	Memory technology devices
2	Mice and other pointing devices
2	Monitors
5	Pretwork adapters
÷	Ports (COM & LPT)
	USB Serial Port (COM6)
- 8	🛱 Print queues
- 1	Processors
- P.	Preservices
3	Smart card readers
ŝ	Software components
÷	Software devices
- 8	Sound, video and game controllers
	Que Storano controllore

In this case the standard setting was COM6.

- Double click on "USB Serial Port (COMx)"
- 1. Go to the "Port settings" and make sure that the settings are according to the image below

1	Bits per second.	38400	
	Data bits:	8	-
	Parity:	None	-
	Stop bits:	2	-
	Flow control:	None	-
	2	vancedF	Restore Defaults


2. In case the COM port number is not 1, enter the "Advanced" menu.

Here you can change the COM port number to 1.

3. When all adjustments are done press OK.



When the COM port number was changed you will notice this in the device manager list. You can now clearly find "USB Serial Port (COM1)".




This setting will be saved for future projects. This does not need to be adjusted every time that the USB is reconnected.

pCONet card configuration via PC

Now you can start configurating the pCONet card via the BACset software.

- Open the BACset program.
- 4. Select "MS/TP"
- 5. Select "No router"
- 6. Press "OK"





BACse	1.7 10 10	OWeb/pCOnet			- dates
Cset for pCOW/eb/pCOn	-	ws 8/10 v2.15.4 - Re	started - MS/TP		-
COWeb Device Instanc	e 77000	_ 1			
Device Objects	Notify Classes	Schedules Ca	alendars Test Da	atabase System	Plugin
Read	Write Fact	ory		UTC Time Sync	Time Sync
Read/Write Statu	\$ %				Cancel
Factory Set	ttings:				
MS/TP Baud Rate *	38400 👻		MS/TP Station Address	0	(0 to 127)
© Enable /		Instance Wite	Max Master	127	(0 to 127)
		(0 to 4194303)	Max Info Frames	20	(0 to 255)
Device Instance Object Name	77000 pC0net@77000	(0.004134303)	Firmwar	-	
Description	Carel BACnet Gates	430		App Softwar	e
Location	Unknown				
APDU Timeout	5000	milliseconds	Alarm Enabled	C Yes • No	
APDU Retries	3	(0 to 255)		105 101 110	
Password for Restart	1234				
Local Date/Time	7777.77.77 (777) 7	7:77:77	1		
Daylight Savings Time	🔿 Yes 💿 No				
UTC Offset	0	minutes (-720 to +7	20)		
nterval to send WhoIs	1	minutes (0=none)			
Max Analog Vars*	207 Max Integ	er Vars* 207 M	lax Digital Vars* 207 Max	Total Vars 0	Reboot
				* Must reboot	

1. Make sure that the pCOWeb Device Instance is set to 7700 according to the factory settings.

2. Press the "Read" button.

The progress bar wil count to 100% and will mention "Read complete". The right LED of the pCONet card will start fleshing green. This means that the communication is established between the card and the PC.

Once the read is complete, you will see a text stating that the device was started in Factory Mode until next reboot (see below). You can also see the present settings of the card in this text. Now you can adjust the different parameters.

ACset for pCDW/eb/pCOr	A DAC WD) Mr. 4	0/10 - 215 1	Destand MC/TO			
COWeb Device Instance			Restarted • M5/TP			
		-				
Device Objects	_	Schedules	Calendars Test	Dat	abase System	
Read	Write Fact	ory			UTC Time Sync	Time Sync
Read/Web Statu	t 100 % R	ead Complete				Cancel
De oce Set	ttings for 77000.	This dev	ice was started in Facto	ry Mode un	til nest reboot	
	1		=77000, Station Addr=0	2.0		Baud=38400
MS/TP Baud Rate *	38400 -		MS/TP Station /	Address	0	(0 to 127)
C Enable /	Disable Device	Instance Wide		Master	127	(0 to 127)
Device Instance	77000	(0 to 4194303)	Max Info	Frames	20	(0 to 255)
Object Name	pC0net77000	(0.0.4104000)		Firmware	A207-B207	
Description	Carel BACnet Gates	at Set		10.00000000000	App Softwar	e 2.15.48
Location	Unknown	197				
APDU Timeout	5000	miliseconds	Alarm	Enabled	C Yes @ No	
APDU Retries	3	(0 to 255)	Contraction	LINDUNUS	1. Tes 1. NO	
Password for Restart	1234					
Local Date/Time	1970-1-1 (Thu) 00:1	2:47	_			-
Daylight Savings Time	C Yes @ No					2
UTC Offset	0	minutes (-720 to	+720)			
Interval to send Whols	1	minutes (0-none)			
Max Analog Vars*	207 Max Integ	er Vars* 207	Max Digital Vars* 207	Max T	otal Vars 621	Reboot
Interface Protocol *	Carel				* Must reboot	

1. When you adjust the basic settings, you will have to push the "Write" button to overide the present setting. After pressing the button, the status will count to 100% again to indicate that the writing was finished. If you do not press the button, the adjustments will be lost.

2. When you adjusted major settings (indicated with a *) you will have to reboot the pCONet card. Press the "Reboot" button. Rebooting will take about 1 minute.

COMMON CONNECTION ERRORS

Searching for wrong device instance

This will give the "read error 114". Start the controller again while pushing the setup button for a factory start up. Now you are sure you can find the controller with device instance 77000.

Device	Objects M	lotify Classe	s Schedules	Calendars	Test	Database	System	Plugin
Rea	atin W be	• F	ctory			UTC Time	Sync	Time Sync
Read/	Write Status	0 %	?Read Error [-1	14]?: InvalidDestin	nationAddr at C	bject Name		Cancel

Wrong polarity of the RS485-USB convertor


This will give the "read error 111". Check the wiring from the convertor and make sure that the wiring is correct. The wiring should be as follows:

Rx+/Tx+ --> + Rx-/Tx- --> -

Device	Objects	Notity Class	es Schedules	Calendars	Test	Database	System	Plugin
Re	od V	Vrite F	actory			UTC Time	Sync	Time Sync
Read	Awhite Status	0 %	?Read Error [-111]?: Timeout at Obj	ect Name			Cancel
	Device Settin	ngs for 77000.						

COM Port settings not correct

The message underneath will be presented if the COM Port settings are not correct.



Make sure that the settings are adjusted as given previously (see "Adjust Port Settings"). The most common error is that the port was not adjusted to COM Port 1.

TEST VIA BACSET

You can test if the configuration was executed correctly by ckecking if you can read all the different addresses from the Carel PLC in the BACset software.

- 1. Go to the tab "Test"
- 2. Click on "Read"



BACset for pCOWeb/pCOnet BACnet®	CAREL
tel for pCOWeb/pCOnet BACnet(R) Windows 8/10 v2.15.4 - Restated - MS/TP	
OWeb Device Instance 77003	
Device Objects NoBy Classes Schedules Calendars Test D	tabase System Plugin
Read Statue 5	Cancel
AV 1 to AV 207 V AV/MV 1001 to AV/MV 1207	✓ BV 1 to BV 207
Bude • Object D © ObjectD/ObjectName/Links © Description/Links bjjID PresentValue	Show Unveilable Values

The software will start reading all different addresses. You can follow the progress in the Read Status section. The read is completed when the status is 100%.

The different values will be presented.

AGset for pCOWeb/pCOnet ((ACenet(R)) Windowe 3/10 v2.15.4	H D
BACset for pCOWeb/pCOnet BACnet®	CAREL
Cset for pCOWeb/pCOnet BACnet(R) Windows 8/10 v2 15.4 - Restarted - MS/TP	
00Web Device Instance 77000	
Device Ditencts Notity Classes Schedules Calendars Test Database Read Clear	System Plugin
Read Statut 100 % Read Complete	Cancel
AV 1 10 AV 207 2 AV/MV 1001 to AV/MV 1207 2 BV	
nclude ⊂ Object ID © ObjectID/ObjectName/Links © Description/Umits 08130: PresentValue	Show Unreliable Values
AV001 27, 400000 AV002 31, 400000 AV002 14, 400000 AV002 15, 400000 AV005 28, 400000 AV005 28, 000000 AV005 30, 000000 AV005 30, 000000 AV005 30, 000000 AV010 30, 000000 AV011 30, 000000 AV012 25, 000000 AV012 25, 000000 AV012 26, 000000 AV012 0, 000000 AV014 0, 000000 AV015 0, 000000 AV014 0, 000000 AV015 0, 000000 AV012 0, 000000 AV014 0, 000000 AV01	•
25-2017 Carel Industries SpA, All Fights Reserved	

According to our communication table we get the next values

Fluid outlet temperature	27,4 °C
Ambient temperature	31,4°C
AD switchpoint 1	24°C
AD switchpoint 2	28°C

•••

				BACNET IF	2	BA	ACNET MS/	TP
Variable	NON	R/W	Obj_ Type	Obj_ Instance	Obj_ Name	Obj_ Type	Obj_ Instance	Obj_ Name
Fluid outlet temperature	*C	R	analog	100001	A0001	analog	1	A001
Ambient temperature	°C	R	analog	100003	A0003	analog	3	A003
AD switchpoint 1	*C	R/W	analog	100004	A0004	analog	4	A004
AD switchpoint 2	*C	R/W	analog	100005	A0005	analog	5	A005
Low speed mode: maximum fan speed	*C	R/W	analog	100007	A0007	analog	7	A007
Low speed mode: AD switchpoint 1	°C	R/W	analog	100008	A0008	analog	8	A008
Low speed mode: AD switchpoint 2	°C	R/W	analog	100009	A0009	analog	9	A009



TVFC-OT

FURTHER ASSISTANCE & INFORMATION

More information

REFERENCE LITERATURE

- Eurovent 9-5 (6) Recommended Code of Practice to keep your Cooling System efficient and safe. Eurovent/Cecomaf, 2002, 30p.
- Guide des Bonnes Pratiques, Legionella et Tours Aéroréfrigérantes. Ministères de l'Emploi et de la Solidarité, Ministère de l'Economie des Finances et de l'Industrie, Ministère de l'Environnement, Juin 2001, 54p.
- Voorkom Legionellose. Minsterie van de Vlaamse Gemeenschap. December 2002, 77p.
- Legionnaires' Disease. The Control of Legionella Bacteria in Water Systems. Health & Safety Commission. 2000, 62p.
- Hygienische Anforderungen an raumlufttechnische Anlagen. VDI 6022.

INTERESTING WEBSITES

Baltimore Aircoil Company	www.BaltimoreAircoil.com
BAC Service website	www.BACservice.eu
Eurovent	www.eurovent-certification.com
European Working Group on Legionella Infections (EWGLI)	EWGLI
ASHRAE	www.ashrae.org
Uniclima	www.uniclima.fr
Association des Ingénieurs et techniciens en Climatique, Ventilation et Froid	www.aicvf.org
Health and Safety Executive	www.hse.gov.uk

ORIGINAL DOCUMENTATION

This manual is originally made in English. Translations are provided for your convenience. In the event of discrepancies, the English original text shall prevail over the translation.

The service expert for BAC equipment

We offer tailored services and solution for BAC cooling towers and equipment.

- · Original spare parts and fill -for an efficient, safe and year round reliable operation.
- Service solutions preventive maintenance, repairs, refurbishments, cleaning and disinfection for reliable trouble-free operation.
- Upgrades and new technologies save up energy and improve maintenance by upgrading your system.
- Water treatment solutions equipment for controlling corrosion scaling and proliferation of bacteria.

For more details, contact your local BAC representative for further information and specific assistance at www.BACservice.eu





BAC

L	





BAC

L	





BAC

L	

COOLING TOWERS

CLOSED CIRCUIT COOLING TOWERS

ICE THERMAL STORAGE

EVAPORATIVE CONDENSERS

HYBRID PRODUCTS

PARTS, EQUIPMENTS & SERVICES

BLUE by nature GREEN at heart



www.BaltimoreAircoil.com Europe@BaltimoreAircoil.com

Please refer to our website for local contact details.

Industriepark - Zone A, B-2220 Heist-op-den-Berg, Belgium

© Baltimore Aircoil International nv